Doug Fleenor RS232 to DMX Lighting Control Module Help

General Information	
SimplWindows Name:	Doug Fleenor RS232 to DMX Lighting
	Control
Category:	Miscelleanous
Version:	1.0
Summary:	This module allows you to send analog values to control up to 16 channels on a DMX512 compatible light fixture using the Doug Fleenor RS232 to DMX512 interface. In addition, you can poll the device to determine current channel values.
General Notes:	Up to 16 DMX channels can be controlled and/or polled for their value.
Crestron Hardware Required:	2 or 3 Series Processor
Software Requirements	None
Setup of Crestron Hardware:	RS-232 connection between Crestron
	processor and Doug Fleenor RS232 to
	DMX512 interface.
Control	
Channel_1-16_Level	Analog value to set the DMX channel that was passed in via the corresponding parameter input.
Poll_Levels	This digital signal will poll the Doug Fleenor device for the current levels. The number of channels polled is based on the channels used analog input below.
Channels_Used	This analog signal specifies how many channels are used and tells the module how many channels to poll.

From_Device\$	This serial input should be connected	
	to the RX side of a serial port.	
Feedback		
Channel_1-16_Current_Level	Analog Value indicating the current	
	level of the DMX channel that was	
	passed in via the corresponding	
	parameter input.	
Polling_In_Progress	Digital signal indicating polling is	
	currently in progress.	
To_Device\$	This serial output should be connected	
	to the TX side of a serial port.	
Parameters		
Channel1-16	These parameters correspond to the	
	DMX512 channel number that you	
	want to control.	